

BALANCE

UV GEL SYSTEM



Balance Overlay Kit Instructions

For Professional Use Only

Balance UV Gel System allows the nail tech unsurpassed control in perfect color options. The Balance System offers durability, adhesion, flexibility and strength

Natural Nail Prep

Proper preparation of the natural nail and workstation are preventative steps to guard against problems and will help you get the best possible results from your professional nail service.

1. Spray your hands and clients hands with Sanitize and gently massage. Sanitize will help reduce the spread of infection.
2. Apply a very small dollop of NSI 's Vanish Cuticle Dissolve to each cuticle and gently massage. Gently push back the eponychium, and remove any non-living tissue. Wipe excess Vanish from each nail, using a Nail Wipe moistened with NSI Cleanse.
3. Remove the shine from the natural nail using NSI Prep 180 grit file following the contour of the nail and moving the file in the direction of nail plate growth.
4. Remove excess dust with the NSI Plush Brush.
5. Using an NSI Nail Wipe saturated with Nail Pure Plus, press and rub into natural nail, sidewalls, and under free edge to remove oil, moisture, and contaminants. Allow natural nail to become chalky white.
6. If extensions are desired, adhere tip or fit form at this time.
7. Apply Balance Bond (Acid-Free) Primer liberally to the natural nail. Remove the brush from the bottle and wipe along the edge of the bottle, then brush onto two natural nails. Re-dip the brush and repeat the process until the nails are coated. Allow to dry for one minute. They will not appear chalky white.

Natural Nail Overlay or Tip and Overlay

1. Using the flattened side of a #5 or #7 Touch Tip Brush, gather a small amount of any of the Balance Builder or Body Builder Gels.
2. Starting in zone 3, brush the entire length of the nail being sure to coat the nail evenly with a thin "lock-in" base layer.

Note: If the first layer is applied too thick it could prevent proper adhesion.

3. Cure in NSI Ultra Professional Full Hand Lamp for 90 seconds.
4. Do not remove tacky dispersion layer.
5. Apply a second coat of gel if necessary. This depends on the desired length, activity level and fashion preference of the client.
6. Check the nail from all angles to ensure proper apex placement. Add a small amount of gel to the upper arch, if necessary.
7. Cure for 90 seconds.
8. Wipe off tacky dispersion layer using an NSI Nail Wipe lightly saturated with NSI Cleanse.
9. Refine surface using light buffing and gentle filing, if necessary.
10. Remove excess dust with NSI Plush Brush.
11. Use an NSI Nail Wipe lightly saturated with NSI Cleanse to remove any dust that may be hiding in sidewalls.
12. Using the flattened side of the Touch Tip Brush of your choice, apply a medium amount of Finish Clear to the entire surface making sure to seal and cap all edges.
13. Cure for 90 seconds.
14. Remove tacky dispersion layer using an NSI Nail Wipe lightly saturated with NSI Cleanse.
15. Condition surrounding skin with Nurture Oil.

Natural Nail Overlay and Tip & Overlay with Brush On French White

1. Using the flattened side of a #5 or #7 Touch Tip Brush, gather a small amount of any of the Balance Builder or Body Builder Gels.
2. Starting in zone 3, brush the entire length of the nail being sure to coat the nail evenly with a thin "lock-in" base layer.

Note: If the first layer is applied too thick it could prevent proper adhesion.

3. Cure in UV lamp for 90 seconds.
4. Wipe off tacky dispersion layer using an NSI Nail Wipe lightly saturated with NSI Cleanse.
5. Using the point of the #5 or #7 Touch Tip Brush, dip into the container of the Brush On French White Gel and pick up a small to medium amount of gel. Keep the gel on the tip of the brush. The gel will be the consistency of nail polish.
6. Starting with the thumb, brush onto the nail creating a smile line. Use techniques similar to "polishing" for a French look.
7. Wipe any gel residue from brush on a clean lint-free NSI Nail Wipe.
8. Back brush smile line if necessary to make a smooth crisp line.
9. "Freeze" or "lock" smile line in place using the Ultra Pro Full Hand UV Lamp for 10 seconds.
10. Repeat process on nails of one hand until all smile lines have been created and "frozen" or "locked".
11. Cure the nails of one hand in an Ultra Pro Full Hand UV Lamp for 120 seconds (2 minutes).

NOTE: The Brush On French White is recommended to be cured for 120 seconds (2 minutes) in an Ultra Pro Full Hand UV Lamp.

12. Using the flattened side of a #5 or #7 Touch Tip Brush, gather a small amount of Balance Builder or Body Builder Clear Gel.
13. Starting in zone 3, and keeping the brush parallel to the nail, stretch and pull the gel over the entire length of the nail using a light "floating" touch.
14. Check for proper apex placement, and add a small amount of gel to the upper arch, if necessary.
15. Cure in NSI Ultra Professional Full Hand Lamp for 90 seconds.
16. Wipe off tacky dispersion layer using an NSI Nail Wipe lightly saturated with NSI Cleanse.
17. Refine surface using light buffing and gentle filing, if necessary.
18. Remove excess dust with NSI Plush Brush.
19. Use an NSI Nail Wipe lightly saturated with NSI Cleanse to remove any dust that may be hiding in sidewalls.
20. Using the flattened side of the Touch Tip brush of your choice, apply a medium amount of Finish Clear to the entire surface making sure to seal and cap all edges.
21. Cure for 90 seconds.
22. Remove tacky dispersion layer using an NSI Nail Wipe lightly saturated with NSI Cleanse.
23. Condition surrounding skin with Nurture Oil.

All NSI products are developed and manufactured by NSI and are designed for professional use only.

All NSI products must be kept at room temperature (65°-80°F)

WARNING:

Professional use only. May cause irritation of skin and eyes. In case of eye contact, flush with water. If skin irritation occurs, discontinue use. In case of emergency, retain product packaging and contact a physician or Infotrac Chemical Emergency Response at 1-800-535-5053 or 1-352-323-3500 immediately. UV curable - Keep out of direct sunlight.

Made in USA by NSI

W. Conshohocken, PA 19428

Tel: 800.354.6741 • 610.825.1524 • Fax: 610.825.2738

www.nsinails.com

9 RUE DU MONITEUR, B-1000, BRUSSELS, BELGIUM